

GSFC JPSS CMO
August 05, 2015
Released

Effective Date: July 28, 2015
Block/Revision 0200C

Joint Polar Satellite System (JPSS) Ground Project
Code 474
474-00448-02-28-B0200

Joint Polar Satellite System (JPSS)
Algorithm Specification Volume II: Data
Dictionary for the OMPS Limb RDR

Block 2.0.0



National Aeronautics and
Space Administration

Goddard Space Flight Center
Greenbelt, Maryland

Joint Polar Satellite System (JPSS) Algorithm Specification

Volume II: Data Dictionary for the OMPS Limb RDR

JPSS Review/Approval Page

Prepared By:

JPSS Ground System
(Electronic Approvals available online at https://jpssmis.gsfc.nasa.gov/frontmenu_dsp.cfm)

Approved By:

Robert M. Morgenstern Date
JPSS Ground Project Mission Systems Engineering Manager
(Electronic Approvals available online at https://jpssmis.gsfc.nasa.gov/frontmenu_dsp.cfm)

Approved By:

Daniel S. DeVito Date
JPSS Ground Project Manager
(Electronic Approvals available online at https://jpssmis.gsfc.nasa.gov/frontmenu_dsp.cfm)

**Goddard Space Flight Center
Greenbelt, Maryland**

Preface

This document is under JPSS Ground ERB configuration control. Once this document is approved, JPSS approved changes are handled in accordance with Class I and Class II change control requirements as described in the JPSS Configuration Management Procedures, and changes to this document shall be made by complete revision.

Any questions should be addressed to:

JPSS Configuration Management Office
NASA/GSFC
Code 474
Greenbelt, MD 20771

Change History Log

Revision	Effective Date	Description of Changes (Reference the CCR & CCB/ERB Approve Date)	Sections Affected
0200-	August 22, 2013	This version incorporates 474-CCR-13-1177 which was approved by JPSS Ground ERB on the effective date shown.	All
0200A	Jan 23, 2014	This version incorporates 474-CCR-13-1459 which was approved by JPSS Ground ERB on the effective date shown.	All
0200A1	Oct 23, 2014	This version incorporates 474-CCR-14-2091 which was approved by the JPSS Ground ERB for CO10 on the effective date shown.	All
0200B	Oct 23, 2014	This version incorporates 474-CCR-14-2168 and 474-CCR-14-2072 which was approved by the JPSS Ground ERB on the effective date shown.	All
0200C	Jul 28, 2015	This version incorporates 474-CCR-15-2288 and 474-CCR-15-2506 which was approved by the JPSS Ground ERB on the effective date shown.	All

List of TBx Items

TBx	Type	ID	Text	Action
1	TBD	SRS.02.28_90	<p>The following paragraphs describe the structure and contents of the RDR granules formed by the JPSS ground processing software. The ground processing software generates several RDRs for each sensor by accumulating one or more specific APs into a single collection. The accumulated APs are not byte-aligned or otherwise altered. They are merely collected and placed into storage in the order that they are received. The following paragraphs describe the binary packaging structure for these accumulated APs. Table 4-1, Common RDR Structure, shows the common JPSS RDR Structure. All JPSS RDRs are based on the same generic granule storage framework and is illustrated conceptually in Figure 4-1 Common RDR Layout.</p> <p>The detailed structure and contents of the APs are documented in the Mission Data Format Control Book (MDFCB) for each mission, GSFC 429-05-02-42 for S-NPP, and 472-TBD2 for JPSS-2. For more information on AP formatting, see the Recommendations for Advanced Orbiting Systems, Networks and Data Links, CCSDS 701.0-B-2, Section</p>	Define Document number for JPSS-2

TBx	Type	ID	Text	Action
			3.3.3. Note: All multi-byte structures are in Big Endian.	
2	TBD	SRS.02.28_119	Table 4.3.2-1, OMPS LP Science RDR Application Packets, lists the APs accumulated for the OMPS LP Science RDR. In the event of a discrepancy in the APIDs listed here, see the MDFCB, GSFC 429-05-02-42 for S-NPP, or 472-TBD for JPSS-2.	Define Document number for JPSS-2
3	TBD	SRS.02.28_126	Table 4.4.2-1, OMPS LP Calibration RDR Application Packets, lists the APs accumulated for the OMPS LP Calibration RDR. The APID assignment listed in Table 4.4.2-1, OMPS LP Calibration RDR Application Packets, applies to S-NPP only. In the event of a discrepancy in APIDs listed here, see the MDFCB, GSFC 429-05-02-42 or 472-TBD for JPSS-2.	Define Document number for JPSS-2
4	TBD	SRS.02.28_133	Table 4.5.2-1, OMPS LP Diagnostic Exposure #1 Earth View RDR Application Packets, lists the APs accumulated for the OMPS LP Diagnostic Exposure #1 Earth View RDR. In the event of a discrepancy in APIDs listed here, see the MDFCB, GSFC 429-05-02-42 or 472-TBD for JPSS-2.	Define Document number for JPSS-2
5	TBD	SRS.02.28_140	Table 4.6.1-1, OMPS LP Diagnostic Exposure #2 Earth View RDR Application Packets, lists the APs accumulated for the OMPS LP Diagnostic Exposure #2 Earth View RDR. In the event	Define Document number for JPSS-2

TBx	Type	ID	Text	Action
			of a discrepancy in the APIDs listed here, see the MDFCB, GSFC 429-05-02-42 for S-NPP, or 472-TBD for JPSS-2.	
6	TBD	SRS.02.28_62487	Table 4.7.2-1, OMPS LP Diagnostic Calibration RDR Application Packets, lists the APs accumulated for the OMPS LP Diagnostic Calibration RDR. In the event of a discrepancy in APIDs listed here, see the MDFCB, GSFC 429-05-02-42 or 472-TBD for JPSS-2.	Define Document number for JPSS-2

Table of Contents

1	Introduction.....	1
1.1	Scope.....	1
1.2	Organization.....	1
2	Related Documentation.....	2
2.1	Parent Documents	2
2.2	Applicable Documents.....	2
2.3	Information Documents	2
3	UML for HDF5 Products	4
3.1	RDR HDF5 Details	4
3.2	TDR/SDR HDF5 Details	6
4	JPSS Raw Data Records (RDRs).....	9
4.1	Common RDR Structures	10
4.2	OMPS Limb Profile (LP) RDR Overview.....	13
4.3	OMPS LP Science RDR	14
4.3.1	OMPS LP Science RDR HDF5 Files	14
4.3.2	OMPS LP Science RDR Data Content Summary.....	14
4.4	OMPS LP Calibration RDR.....	15
4.4.1	OMPS LP Calibration RDR HDF5 Files	15
4.4.2	OMPC LP Calibration RDR Data Content Summary	15
4.5	OMPS LP Diagnostic Exposure #1 Earth View RDR	16
4.5.1	OMPS LP Diagnostic Exposure #1 Earth View RDR HDF5 Files	16
4.5.2	OMPS LP Diagnostic Exposure #1 Earth View RDR Data Content Summary	16
4.6	OMPS LP Diagnostic Exposure #2 Earth View RDR	17
4.6.1	OMPS LP Diagnostic Exposure #2 Earth View RDR HDF5 Files	17
4.7	OMPS LP Diagnostic Calibration RDR	18
4.7.1	OMPS LP Diagnostic Calibration RDR HDF5 Files.....	18
4.7.2	OMPS LP Diagnostic Calibration RDR Data Content Summary.....	18
4.8	OMPS Dwell RDR.....	19
4.9	OMPS Telemetry RDR	19
4.10	OMPS Memory Dump RDR.....	19
4.11	OMPS Flight Software (FSW) Boot-up Status RDR.....	19
5	Temperature Data Records (TDRs)	20
6	Sensor Data Records (SDRs)	21
7	Look-up Tables and Processing Coefficient Tables	22
7.1	Look-up Tables	22
7.1.1	OMPS Limb RDR LUTs	22

7.2	Processing Coefficient Tables.....	22
7.2.1	Automated Processing Coefficients	22
7.2.1.1	OMPS Limb RDR Automated PCs	22
7.2.2	Manual Processing Coefficients	22
7.2.2.1	OMPS Limb RDR Initialization PCs	22
7.2.2.2	OMPS Limb RDR Ephemerical PCs	22
8	Intermediate Products (IPs).....	23
Appendix A.	Data Mnemonic to Interface Mapping.....	24
Appendix B.	Common RDR Static Header Values.....	25
Appendix C.	DQTT Quality Flag Mapping	26
Appendix D.	Abbreviations and Acronyms	27
Attachment A.	XML Formats for Related Data products	28

List of Figures

Figure: 3.1-1	Science and Diagnostic RDR Generalized UML Diagram.....	5
Figure: 3.1-2	Dwell, Dump, Telemetry, and Spacecraft Diary (when requested separately) RDR Generalized UML Diagram	6
Figure: 3.2-1	Generalized UML Diagram for HDF5 SDR/TDR Files	8
Figure: 4-1	Common RDR Layout	10

List of Tables

Table: 4-1	Common RDR Structure	9
Table: 4.1-1	RDR Static Header	11
Table: 4.1-2	RDR APID List	12
Table: 4.1-3	Application Packet Storage Area	12
Table: 4.1-4	Application Packet Tables	12
Table: 4.3.2-1	OMPS LP Science RDR Application Packets.....	14
Table: 4.3.2-2	OMPS LP Science RDR Structure	15
Table: 4.4.2-1	OMPS LP Calibration RDR Application Packets	15
Table: 4.4.2-2	OMPS LP Calibration RDR Maximum Sizes	15
Table: 4.4.2-3	OMPS LP Calibration RDR Structure.....	16
Table: 4.5.2-1	OMPS LP Diagnostic Exposure #1 Earth View RDR Application Packets	16
Table: 4.5.2-2	OMPS LP Diagnostic Exposure #1 RDR Structure	17
Table: 4.6.1-1	OMPS LP Diagnostic Exposure #2 Earth View RDR Application Packets	17
Table: 4.6.1-2	OMPS LP Diagnostic Exposure #2 RDR Structure	18
Table: 4.7.2-1	OMPS LP Diagnostic Calibration RDR Application Packets	18
Table: 4.7.2-2	OMPS LP Diagnostic Calibration RDR Structure	19
Table: ATT-1	XML Formats for Related Products	28

1 Introduction

1.1 Scope

The Joint Polar Satellite System (JPSS) Algorithm Specification for OMPS Limb RDR – Volume II: Data Dictionary contains the specifications for the format of the OMPS Limb Raw Data Records (RDRs). This specification includes the format of the Hierarchical Data Format Release 5 (HDF5) files, as well as the product definitions. These formats are available to external users of the JPSS. For an overview of the data product formats, see 474-00001-01, JPSS CDFCB-X Vol I. For an overview of the metadata formats for data products, see 474-00448-02-01, JPSS Algorithm Specification Volume II: Data Dictionary for the Common Algorithms.

1.2 Organization

Section	Contents
Section 1	Provides information regarding the scope, and organization of this document, as reference material only.
Section 2	Lists parent documents and related documents that were used as sources of information for this document or that provide additional background information to aid understanding of the interface implementations.
Section 3	Provides an overview of the HDF5 UML for the data product types.
Section 4	Provides a description of the contents of each JPSS RDR.
Section 5	Provides a description of the contents of each JPSS TDR if applicable.
Section 6	Provides a description of the contents of each JPSS SDR if applicable.
Section 7	Provides a description of relevant Look-Up Tables (LUTs) and Processing Coefficient Tables (PCTs).
Section 8	Provides a description of each Intermediate Product if applicable.
Appendix A	Provides the Data Mnemonic to Interface Mapping for the data products in this volume.
Appendix B	Provides common RDR static header values in this volume.
Appendix C	Provides a mapping of the quality flags by sensor and product that are reportable to the associated data product quality flag Test ID used in the processing environment.
Appendix D	Provides reference to acronyms and glossary of terms found within the JPSS Program Lexicon (470-00041).
Attachment A	Provides the list of applicable xml files for this Data Dictionary.

2 Related Documentation

The latest JPSS documents can be obtained from URL:

https://jpssmis.gsfc.nasa.gov/frontmenu_dsp.cfm. JPSS Project documents have a document number starting with 470, 472 or 474 indicating the governing Configuration Control Board (CCB) (Program, Flight, or Ground) that has the control authority of the document.

2.1 Parent Documents

The following reference document(s) is (are) the Parent Document(s) from which this document has been derived. Any modification to a Parent Document will be reviewed to identify the impact upon this document. In the event of a conflict between a Parent Document and the content of this document, the JPSS Program Configuration Change Board has the final authority for conflict resolution.

Document Number	Title
474-00448-01-28	JPSS Algorithm Specification Volume I: Software Requirements Specification (SRS) for the OMPS Limb RDR

2.2 Applicable Documents

The following document(s) is (are) the Applicable Document(s) from which this document has been derived. Any modification to an Applicable Document will be reviewed to identify the impact upon this document. In the event of conflict between an Applicable Document and the content of this document, the JPSS Program Configuration Change Board has the final authority for conflict resolution.

Document Number	Title
NPR 7150.2A	NASA Software Engineering Requirements
474-00167	Joint Polar Satellite System (JPSS) Common Ground System (CGS) Requirements Document
474-00005	Joint Polar Satellite System (JPSS) Government Resource for Algorithm Verification, Independent Testing, and Evaluation (GRAVITE) Requirements Document
474-00448-04-28	Joint Polar Satellite System (JPSS) Algorithm Specification Volume IV: Software Requirements Specification Parameter File (SRSPF) for the OMPS Limb RDR
N/A	Hierarchical Data Format, Version 5 (HDF5), http://www.hdfgroup.org/HDF5/

2.3 Information Documents

The following documents are referenced herein and amplify or clarify the information presented in this document. These documents are not binding on the content of this document.

Document Number	Title
474-00333	Joint Polar Satellite System (JPSS) Ground System (GS) Architecture Description Document (ADD)
474-00054	Joint Polar Satellite System (JPSS) Ground System (GS) Concept of Operations (ConOps)
470-00041	Joint Polar Satellite System (JPSS) Program Lexicon

Document Number	Title
474-00001-01	Joint Polar Satellite System (JPSS) Common Data Format Control Book, Vol I – Overview
474-00448-02-01	Joint Polar Satellite System (JPSS) Algorithm Specification Volume II: Data Dictionary for the Common Algorithms
429-05-02-42	Joint Polar Satellite System (JPSS) Mission Data Format Control Book for NPP

3 UML for HDF5 Products

3.1 RDR HDF5 Details

Figure 3.1-1, Science and Diagnostic RDR Generalized UML Diagram, depicts the HDF5 RDR file organization as a Unified Modeling Language (UML) class diagram for Science and Diagnostic RDRs. This also describes the science calibration RDRs generated by OMPS. Figure 3.1-2, Dwell, Dump, and Telemetry RDR Generalized UML Diagram, depicts the HDF5 RDR file organization as a UML Class Diagram for Dwell, Dump and Telemetry RDRs.

Each HDF5 RDR file contains an HDF5 Root Group, ‘/’, a Data_Products Group, one or more Product Groups (CollectionShortName), and an All_Data Group containing one or more (CollectionShortName)_All groups. The latter group contains the Dataset_Array which holds the common RDR structures of Consultative Committee for Space Data Systems (CCSDS) structured APs. For Science and Diagnostic RDRs a Spacecraft Diary Group is also included in the Data_Products group. The Product Groups and Spacecraft Diary Group both contain datasets – an Aggregation Dataset (CollectionShortName_Aggr) and Granule Datasets (CollectionShortName_Gran_n – where n indicates the nth granule in a temporal aggregation of granules (1 .. n)). A granule is a general term used to describe the minimum quanta of data collected per processing period, generally on the order of seconds. For the definition and organization of the metadata attributes contained in the HDF5 files, see 474-00448-02-01, JPSS Algorithm Specification Volume II: Data Dictionary for the Common Algorithms. Attributes that are specific to a particular RDR are listed with the specific RDR’s data format definition. Note: In the UML diagrams, an ‘*’ following the name of an attribute indicates an element with exceptions; see JPSS Algorithm Specification Volume II: Data Dictionary for the Common Algorithms, for the details of the exception.




Figure: 3.1-1 Science and Diagnostic RDR Generalized UML Diagram




Figure: 3.1-2 Dwell, Dump, Telemetry, and Spacecraft Diary (when requested separately) RDR Generalized UML Diagram

3.2 TDR/SDR HDF5 Details

Figure 3.2-1, Generalized UML Diagram for HDF5 SDR/TDR Files, depicts the HDF5 SDR/TDR organization as a Unified Modeling Language (UML) class diagram. Each HDF5 SDR/TDR file contains an HDF5 Root Group, ‘/’, a Data Products Group, Product Groups (Collection Short Name), an optional Geolocation Group (depending upon packaging option, see the JPSS CDFCB-X Vol. I for a description of the geolocation packaging), and an All Data Group (dataset arrays). The Product Groups and Geolocation Group both contain datasets - an

Aggregation Dataset (Collection Short Name_Aggr) and Granule Datasets (Collection Short Name_Gran_n) - where n indicates the nth granule in a temporal aggregation of granules (1 .. n). A granule is a general term used to describe the minimum quanta of data collected per processing period, generally on the order of seconds. For the definition and organization of the metadata attributes contained in the HDF5 files, see 474-00448-02-01, JPSSAlgorithm Specification Volume II: Data Dictionary for the Common Algorithms. Attributes that are specific to a particular SDR/TDR are listed with the specific SDR/TDR's data format definition. For the generalized formats and packaging options for the Geolocation data, see the JPSS CDFCB-X Vol. I.




Figure: 3.2-1 Generalized UML Diagram for HDF5 SDR/TDR Files

4 JPSS Raw Data Records (RDRs)

The following paragraphs describe the structure and contents of the RDR granules formed by the JPSS ground processing software. The ground processing software generates several RDRs for each sensor by accumulating one or more specific Application Packets (APs) into a single collection. The accumulated APs are not byte-aligned or otherwise altered. They are merely collected and placed into storage in the order that they are received. The following paragraphs describe the binary packaging structure for these accumulated APs. Table 4-1, Common RDR Structure, shows the common JPSS RDR Structure. All JPSS RDRs are based on the same generic granule storage framework and is illustrated conceptually in Figure 4-1 Common RDR Layout.

The detailed structure and contents of the APs are documented in the Mission Data Format Control Book (MDFCB) for each mission, GSFC 429-05-02-42 for S-NPP, and 472-TBD2 for JPSS-2. For more information on AP formatting, see the Recommendations for Advanced Orbiting Systems, Networks and Data Links, CCSDS 701.0-B-2, Section 3.3.3.

Table: 4-1 Common RDR Structure

Field Name	Description
Static Header	Static header describing the RDR
APID List	Array of structures that contains information about each APID that is collected in the RDR
Packet Tracker	Array of structures that contains information about each AP that is in the RDR
AP Storage area	General buffer where the APs are stored back-to-back in the order that they are received




Figure: 4-1 Common RDR Layout

4.1 Common RDR Structures

The following section defines these structures and provides methods for determining the variable length RDR components.

Description/ Purpose	The following tables describe the four structures found in the common RDR Structure. The common RDR Structure granules are referenced by the HDF5 Object and Reference Region pointers in the CollectionShortName_Aggr and CollectionShortName_Gran_# datasets, respectively.
File-Naming Construct	See the JPSS CDFCB-X Vol. I-Overview, Section 3.0 for details.
File Size	Nominally specified per RDR
File Format Type	Big Endian Binary (structure stored within HDF5)
Production Frequency	Common structure created for each RDR granule Granule durations specified per RDR
Data Content and Data Format	Each RDR has a single RDR Static Header and a dynamic Application Packet content area with three major entries: 1) APID List, 2) Packet Tracker List, and 3) Application Packet Storage Area.

	<p>Table 4.1-1, RDR Static Header, details the spacecraft and sensor that the RDR data originated from, the type of data the RDR contains, and the start and end boundary times of the RDR granule. It also provides byte offset information needed to access individual APs and the number of AP types that are contained in the RDR.</p> <p>Tables 4.1-2, 4.1-3, and 4.1-4 define the Dynamic Application Packet content area.</p> <p>Table 4.1-2, RDR APID List, defines the structure used to identify the AP data type and it provides information necessary for accessing the RDR Packet Tracker. The APID List has details for each APID including number expected and received.</p> <p>Table 4.1-3, RDR Packet Tracker provides information about individual APs.</p> <p>Table 4.1-4, Application Packet Storage Area, describes the storage area containing the APs.</p>
--	---

Table 4.1-1, RDR Static Header, details the spacecraft and sensor that the data originated from, the type of the data the RDR contains, and the start and end boundary times of the RDR granule. The RDR contains APs that have observation times which are greater than or equal to the start boundary and less than the end boundary time. The total size of the RDR Static Header is 72 bytes.

Table: 4.1-1 RDR Static Header

Field Name	Data Type	Description
satellite	char[4]	Source satellite name as found in JPSS CDFCB-X Vol. I, Table 3.4.1-1, Spacecraft ID.
Sensor	char[16]	The RDR sensor name in a case-sensitive string (Example: "VIIRS", "ATMS", "CrIS", etc. See Appendix B, Common Static Header Values, for specific values.)
typeID	char[16]	The RDR type in an upper case string (Example: "SCIENCE", "DIAGNOSTIC", "TELEMETRY", "MEMORY DUMP", "DWELL". See Appendix B, Common Static Header Values, for specific values.)
numAPIDs	Uint32	The number of different types of expected APIDs that make the RDR. (numAPIDs is specific for each type of RDR, see Appendix B, Common Static Header Values, for specific values.)
apidListOffset	Uint32	Byte offset of the APID List (this is equivalent to the size of the static header: 72). The APID List starts immediately after the Generic RDR Static Header. Note: Always use this value to find the APID address.
pktTrackerOffset	Uint32	Byte offset from the beginning of the Common RDR to the Packet Tracker list Note: Always use this value to find the Packet Tracker list.
apStorageOffset	Uint32	Byte offset from the beginning of the Common RDR to the AP Storage

Field Name	Data Type	Description
		Note: Always use this value to find the AP Storage.
nextPktPos	Uint32	Byte offset from the beginning of the Application Packet Storage Area (apStorageOffset) to the end of valid data within the Application Packet Storage Area
startBoundary	int64	All APs occur at or after this time in IDPS Epoch Time (IET) format. Note IET begins January 1, 1958 and is measured in microseconds. For more information on IET see JPSS CDFCB-X Vol. I, Section 3.3.1.
endBoundary	int64	The RDR non-inclusive boundary time in IET format. All APs occur before this time.

Table 4.1-2, RDR APID List, details the APIDs that are in the RDR. The number of elements in the list is equal to the numAPIDs field in the RDR Static Header. The size of a single RDR APID list element is 32 bytes.

Table: 4.1-2 RDR APID List

Field Name	Data Type	Description
name	char[16]	Short name describing the data type (Example: M01 for VIIRS. See individual RDR sections for specific values.)
value	Uint32	This field stores an APID that is in the RDR.
pktTrackerStartIndex	Uint32	The first index in the pktTracker array that will contain an AP of this APID. This index is zero based.
pktsReserved	Uint32	This field stores the number of APs reserved for this APID in this RDR. This value accounts for the worst case expected for the temporal granule period. Due to variability in scan rates, the actual number of packets received can be less than the "reserved" and still be 100% complete as shown in the metadata.
pktsReceived	Uint32	The number of APs of this APID that have been received for this RDR

Table 4.1-3 Application Packet Storage Area, describes the AP storage area.

Table: 4.1-3 Application Packet Storage Area

Field Name	Data Type	Description
apStorage	Array of unsigned int8	Storage area where application packets are stored as they arrive in consecutive order

Table 4.1-4, Application Packet Tables, provides explanations of the fields given for each RDR described in the following sections.

Table: 4.1-4 Application Packet Tables

APID Short Name	Description
-----------------	-------------

APID Short Name	Description
Short name of this Application Packet as an upper-case string	Brief description of this application packet

Note: Grouped or segmented packets contain mission data exceeding the size of a single CCSDS packet.

Accessing APs can be achieved in two fashions; Random Access or Sequential Access.

To access APs in random order by AP type:

- Get the range for a specific type of data from the APID List
 - Find desired AP type using name field
 - Get pktTrackerStartIndex
 - Get pktsReserved
- Loop over the elements in Packet Tracker array starting at pktTrackerStartIndex
 - Get offset (if -1 stop processing no packet received)
 - Get size
 - Access the AP by adding the offset to the apStorageOffset value found in the Static Header
 - Extract size (the AP size in bytes) from the AP Storage Area
 - Repeat above for pktsReserved

To access APs in sequential order:

- Get the apStorageOffset from the Static Header to determine memory location for start of APs in AP Storage Area
- Get the nextPktPos from the Static Header (The nextPktPos value indicates the end of valid RDR data within the AP Storage Area)
- Parse AP's manually by reading the primary header, accessing the size of the packet, and accessing the user data section in the CCSDS packet

Repeat until nextPktPos equals current position.

4.2 OMPS Limb Profile (LP) RDR Overview

Data Mnemonic	Limb Profile (LP) Science: RDRE-OMPS-C0032 Calibration: RDRE-OMPS-C0039 Diagnostic Exposure #1 Earth View: RDRE-OMPS-C0054 Diagnostic Exposure #2 Earth View: RDRE-OMPS-C0056 Diagnostic Calibration: RDRE-OMPS-C0055
Description/ Purpose	OMPS uses two primary sensors within a single instrument suite to perform complementary functions for atmospheric ozone monitoring. Total column ozone is retrieved from backscattered UV radiance measurements, using a 2-D Charge-Coupled Device (CCD) system, which points towards the nadir

	and simultaneously observes across the orbital track to provide daily global mapping. An additional CCD focal plane collects nadir data at shorter wavelengths to create a non-EDR profile ozone product for continuity with previous instruments. Profile ozone data is obtained from limb-scattered UV and visible measurements, using a CCD array-based system.
File-Naming Construct	See the JPSS CDFCB-X Vol. I, Section 3.0 for details
File Size	LP Science: See Table 4.3.2-2 OMPS LP Science RDR Structure for size LP Calibration: See Table 4.4.2-3 OMPS LP Calibration RDR Structure for size LP Diagnostic Exposure #1 Earth View: See Table 4.5.2-2 OMPS LP Diagnostic Exposure #1 RDR Structure for size LP Diagnostic Exposure #2 Earth View: See Table 4.6.1-2 OMPS LP Diagnostic Exposure #2 RDR Structure for size LP Diagnostic Calibration: See Table 4.7.2-2 OMPS LP Diagnostic Calibration RDR Structure
File Format Type	HDF5
Data Content and Data Format	Section 4.3 describes the OMPS LP Science RDR Section 4.4 describes the OMPS LP Calibration RDR Section 4.5 describes the OMPS LP Diagnostic Exposure #1 Earth View RDR Section 4.6 describes the OMPS LP Diagnostic Exposure #2 Earth View RDR Section 4.7 describes the OMPS LP Diagnostic Calibration RDR Section 4.8, 4.9, 4.10 and 4.11 reference the JPSS Algorithm Specification Volume II: Data Dictionary for the OMPS Nadir Profile RDR/SDR (474-00448-02-05) for the following OMPS RDRs: 1. OMPS Dwell RDR 2. OMPS Telemetry RDR 3. OMPS Memory Dump RDR 4. OMPS Flight Software (FSW) Boot-Up Status

4.3 OMPS LP Science RDR

4.3.1 OMPS LP Science RDR HDF5 Files

The OMPS LP Science RDR HDF5 files are described in Section 3.0, Raw Data Records HDF5 Details.

4.3.2 OMPS LP Science RDR Data Content Summary

Table 4.3.2-1, OMPS LP Science RDR Application Packets, lists the APs accumulated for the OMPS LP Science RDR. In the event of a discrepancy in the APIDs listed here, see the MDFCB, GSFC 429-05-02-42 for S-NPP, or 472-TBD for JPSS-2.

Table: 4.3.2-1 OMPS LP Science RDR Application Packets

APID Short Name	Description	Value APID ₁₀
LP1	Science LP Image #1 (long)	562
LP2	Science LP Image #2 (short)	563

Each observation is max-sized to accept at most a single segment (256 packets).

Table 4.3.2-2, OMPS LP Science RDR Structure, shows the layout and static contents of the OMPS LP Science RDR.

Table: 4.3.2-2 OMPS LP Science RDR Structure

	Byte	Field	Type	Value
Static Header	0	satellite	char[4]	‘NPP’
	4	sensor	char[16]	‘OMPS-LP’
	20	typeID	char[16]	‘SCIENCE’
	36	numAPIDs	Uint32	2
	40	apidListOffset	Uint32	72
	44	pktTrackerOffset	Uint32	136
	48	apStorageOffset	Uint32	24712
	52	nextPktPos	Uint32	varies
	56	startBoundary	int64	varies
	64	endBoundary	int64	varies
Dynamic	72	APID List	IngSmdCommon_ApidDetailType[2]	varies
	136	Pkt Tracker List	IngSmdCommon_PktTrackerType[1 024]	varies
	24712	AP storage area	Uint8[1048576]	varies
File Size	1,073,288 Bytes			

4.4 OMPS LP Calibration RDR

4.4.1 OMPS LP Calibration RDR HDF5 Files

The OMPS LP Calibration RDR HDF5 files are described in Section 3.0, Raw Data Records HDF5 Details.

4.4.2 OMPC LP Calibration RDR Data Content Summary

Table 4.4.2-1, OMPS LP Calibration RDR Application Packets, lists the APs accumulated for the OMPS LP Calibration RDR. The APID assignment listed in Table 4.4.2-1, OMPS LP Calibration RDR Application Packets, applies to S-NPP only. In the event of a discrepancy in APIIDs listed here, see the MDFCB, GSFC 429-05-02-42 or 472-TBD for JPSS-2.

Table: 4.4.2-1 OMPS LP Calibration RDR Application Packets

APID Short Name	Description	Value APID₁₀
LP_CAL	Science Nadir Profile Calibration	566

OMPS LP Calibration RDRs contain all images for a single event. Each event is made up of a number of images. Each image can be made up of anywhere from 1 Standalone packet to a multiple segmented group. The RDR is max sized to handle data based on the values provided in Table 4.4.2-2, OMPS LP Calibration RDR Maximum Sizes.

Table: 4.4.2-2 OMPS LP Calibration RDR Maximum Sizes

Sizing Parameter	Value
-------------------------	--------------

Sizing Parameter	Value
Max Number of images	250
Maximum segments per image	5

Table 4.4.2-3, OMPS LP Calibration RDR Structure, shows the layout and static contents of the OMPS LP Calibration RDR.

Table: 4.4.2-3 OMPS LP Calibration RDR Structure

	Byte	Field	Type	Value
Static Header	0	satellite	char[4]	'NPP'
	4	sensor	char[16]	'OMPS-LP'
	20	typeID	char[16]	'CALIBRATIO N'
	36	numAPIDs	Uint32	1
	40	apidListOffset	Uint32	72
	44	pktTrackerOffset	Uint32	104
	48	apStorageOffset	Uint32	7680104
	52	nextPktPos	Uint32	varies
	56	startBoundary	int64	varies
	64	endBoundary	int64	varies
Dynamic	72	APID List	IngSmdCommon_ApidDetailType[1]	varies
	104	Pkt Tracker List	IngSmdCommon_PktTrackerType [131840]	varies
	76801 04	AP storage area	Uint8[327680000]	varies
File Size	335,360,104 Bytes			

4.5 OMPS LP Diagnostic Exposure #1 Earth View RDR

4.5.1 OMPS LP Diagnostic Exposure #1 Earth View RDR HDF5 Files

The OMPS LP Diagnostic Exposure #1 Earth View RDR HDF5 files are described in Section 3.0, Raw Data Records HDF5 Details.

4.5.2 OMPS LP Diagnostic Exposure #1 Earth View RDR Data Content Summary

Table 4.5.2-1, OMPS LP Diagnostic Exposure #1 Earth View RDR Application Packets, lists the APs accumulated for the OMPS LP Diagnostic Exposure #1 Earth View RDR. In the event of a discrepancy in APIDs listed here, see the MDFCB, GSFC 429-05-02-42 or 472-TBD for JPSS-2.

Table: 4.5.2-1 OMPS LP Diagnostic Exposure #1 Earth View RDR Application Packets

APID Short Name	Description	Value APID ₁₀
DIA_LP1	Limb Profile Diagnostic Exposure #1 Earth View	578

OMPS LP Diagnostic Exposure #1 RDRs are sized to expect one observation per granule. This observation is max-sized such that it can only be up to 5 segmented groups (5*256 packets) using the OMPS super segmentation approach. The data may be collected at a different rate than

the granule size, so gaps between granule IDs can be expected (does not imply there are data gaps). The minimum granule size was chosen to support flexibility for Diagnostic activities.

Table 4.5.2-2, OMPS LP Diagnostic Exposure #1 RDR Structure, shows the layout and static contents of the OMPS LP Diagnostic Exposure #1 RDR.

Table: 4.5.2-2 OMPS LP Diagnostic Exposure #1 RDR Structure

	Byte	Field	Type	Value
Static Header	0	satellite	char[4]	‘NPP’
	4	sensor	char[16]	‘OMPS-LP’
	20	typeID	char[16]	‘DIAGEXPONE’,
	36	numAPIDs	Uint32	1
	40	apidListOffset	Uint32	72
	44	pktTrackerOffset	Uint32	104
	48	apStorageOffset	Uint32	30824
	52	nextPktPos	Uint32	varies
	56	startBoundary	int64	varies
	64	endBoundary	int64	varies
Dynamic	72	APID List	IngSmdCommon_ApidDetailType[1]	varies
	104	Pkt Tracker List	IngSmdCommon_PktTrackerType[1 280]	varies
	30824	AP storage area	Uint8[1310720]	varies
File Size	1,341,544 Bytes			

4.6 OMPS LP Diagnostic Exposure #2 Earth View RDR

4.6.1 OMPS LP Diagnostic Exposure #2 Earth View RDR HDF5 Files

The OMPS LP Diagnostic Exposure #2 Earth View RDR HDF5 files are described in Section 3.0, Raw Data Records HDF5 Details.

Table 4.6.1-1, OMPS LP Diagnostic Exposure #2 Earth View RDR Application Packets, lists the APs accumulated for the OMPS LP Diagnostic Exposure #2 Earth View RDR. In the event of a discrepancy in the APIDs listed here, see the MDFCB, GSFC 429-05-02-42 for S-NPP, or 472-TBD for JPSS-2.

Table: 4.6.1-1 OMPS LP Diagnostic Exposure #2 Earth View RDR Application Packets

APID Short Name	Description	Value APID₁₀
DIA_LP2	Limb Profile Diagnostic Exposure #2 Earth View	579

OMPS LP Diagnostic Exposure #2 RDRs are sized to expect one observation per granule. This observation is max-sized such that it can only be up to 5 segmented groups (5*256 packets) using the OMPS super segmentation approach. The data may be collected at a different rate than the granule size, so gaps between granule IDs can be expected (does not imply there are data gaps). The minimum granule size was chosen to support flexibility for Diagnostic activities.

Table 4.6.1-2, OMPS LP Diagnostic Exposure #2 RDR Structure, shows the layout and static contents of the OMPS LP Diagnostic Exposure #2 RDR.

Table: 4.6.1-2 OMPS LP Diagnostic Exposure #2 RDR Structure

	Byte	Field	Type	Value
Static Header	0	satellite	char[4]	'NPP'
	4	sensor	char[16]	'OMPS-LP'
	20	typeID	char[16]	'DIAGEXPTW O'
	36	numAPIDs	Uint32	1
	40	apidListOffset	Uint32	72
	44	pktTrackerOffset	Uint32	104
	48	apStorageOffset	Uint32	30824
	52	nextPktPos	Uint32	varies
	56	startBoundary	int64	varies
	64	endBoundary	int64	varies
Dynamic	72	APID List	IngSmdCommon_ApidDetailType[1]	varies
	104	Pkt Tracker List	IngSmdCommon_PktTrackerType[1 280]	varies
	30824	AP storage area	Uint8[310720]	varies
File Size	1,341,544 Bytes			

4.7 OMPS LP Diagnostic Calibration RDR

4.7.1 OMPS LP Diagnostic Calibration RDR HDF5 Files

The OMPS LP Diagnostic Calibration RDR HDF5 files are described in Section 3.0, Raw Data Records HDF5 Details.

4.7.2 OMPS LP Diagnostic Calibration RDR Data Content Summary

Table 4.7.2-1, OMPS LP Diagnostic Calibration RDR Application Packets, lists the APs accumulated for the OMPS LP Diagnostic Calibration RDR. In the event of a discrepancy in APIDs listed here, see the MDFCB, GSFC 429-05-02-42 or 472-TBD for JPSS-2.

Table: 4.7.2-1 OMPS LP Diagnostic Calibration RDR Application Packets

APID Short Name	Description	Value APID₁₀
DIA_CAL	Diagnostic Limb Profile Calibration	582

OMPS LP Diagnostic Calibration RDRs are sized to expect one image per granule. This observation is max-sized such that it can only be up to 5 segmented groups (5*256 packets) using the OMPS super segmentation approach. The data may be collected at a different rate than the granule size, so gaps between granule IDs can be expected (does not imply there are data gaps). The minimum granule size was chosen to support flexibility for Diagnostic activities.

Table 4.7.2-2, OMPS LP Diagnostic Calibration RDR Structure, shows the layout and static contents of the OMPS LP Diagnostic Calibration RDR.

Table: 4.7.2-2 OMPS LP Diagnostic Calibration RDR Structure

	Byte	Field	Type	Value
Static Header	0	satellite	char[4]	'NPP'
	4	sensor	char[16]	'OMPS-LP'
	20	typeID	char[16]	'DIA-CAL'
	36	numAPIDs	Uint32	1
	40	apidListOffset	Uint32	72
	44	pktTrackerOffset	Uint32	104
	48	apStorageOffset	Uint32	30824
	52	nextPktPos	Uint32	varies
	56	startBoundary	int64	varies
	64	endBoundary	int64	varies
Dynamic	72	APID List	IngSmdCommon_ApidDetailType[1]	varies
	104	Pkt Tracker List	IngSmdCommon_PktTrackerType [1280]	varies
	30824	AP storage area	Uint8[1310720]	varies
File Size	1,341,544 Bytes			

4.8 OMPS Dwell RDR

See Section 4.7 of the JPSS Algorithm Specification Volume II: Data Dictionary for the OMPS Nadir Profile RDR/SDR (474-00448-02-05) for the OMPS Dwell RDR.

4.9 OMPS Telemetry RDR

See Section 4.8 of the JPSS Algorithm Specification Volume II: Data Dictionary for the OMPS Nadir Profile RDR/SDR (474-00448-02-05) for the OMPS Telemetry RDR.

4.10 OMPS Memory Dump RDR

See Section 4.9 of the JPSS Algorithm Specification Volume II: Data Dictionary for the OMPS Nadir Profile RDR/SDR (474-00448-02-05) for the OMPS Memory Dump RDR.

4.11 OMPS Flight Software (FSW) Boot-up Status RDR

See Section 4.10 of the JPSS Algorithm Specification Volume II: Data Dictionary for the OMPS Nadir Profile RDR/SDR (474-00448-02-05) for the OMPS Flight Software (FSW) Boot-up Status RDR.

5 Temperature Data Records (TDRs)

Not Applicable

6 Sensor Data Records (SDRs)

Not Applicable

7 Look-up Tables and Processing Coefficient Tables

7.1 Look-up Tables

Algorithm Look-up Table (LUT) files contain tables of pre-computed values used in lieu of real-time algorithm computations to reduce processing resource demands. Table values are typically the result of RTM executions and other environmental model simulations. These data generally cover broad, multi-dimensional parameter spaces which are unique to each algorithm.

7.1.1 OMPS Limb RDR LUTs

The OMPS Limb RDR currently uses no LUTs.

7.2 Processing Coefficient Tables

The S-NPP/JPSS-1 ground system data product generation subsystem uses Processing Coefficient Table (PCT) file parameters. PCT files can be either Automated or Manual coefficient tables. Within the Manual table type are two coefficient classes: Initial and Ephemeral. Sections below describe all three and any tables of that type for the product.

7.2.1 Automated Processing Coefficients

Automated Processing Coefficient (PC) files contain parameters updated and/or created during the processing of the S-NPP/JPSS Data Products by the processing algorithms. The processing environment subsequently uses these files without human review of their contents. Files can be used immediately after creation or in future processing such as the next granule in the production data stream processing.

7.2.1.1 OMPS Limb RDR Automated PCs

The OMPS Limb RDR currently uses no Automated PCs.

7.2.2 Manual Processing Coefficients

Manual Processing Coefficient (PC) files contain parameters used for S-NPP/JPSS Data Product generation which require human review prior to operational processing environment insertion. Manual Processing Coefficients have two classes:

- Initialization PCTs contain infrequently updated initial parameters sets S-NPP/JPSS uses for data product generation.
- Ephemeral PCTs contain frequently updated parameters sets S-NPP/JPSS uses for data product generation

7.2.2.1 OMPS Limb RDR Initialization PCs

The OMPS Limb RDR currently uses no Initialization PCs.

7.2.2.2 OMPS Limb RDR Ephemeral PCs

The OMPS Limb RDR currently uses no Ephemeral PCs.

8 Intermediate Products (IPs)

Not Applicable

Appendix A. Data Mnemonic to Interface Mapping

For a complete list of Data Mnemonic to Interface Mapping, see 474-00001-01, JPSS CDFCB-X Vol I. The CDFCB contains Data Mnemonics, Identifiers, Collection Short Names, Interface Documents, and Collection Long Names for each JPSS Data Product and for Geolocation data.

Appendix B. Common RDR Static Header Values

Common RDR Static Header Values lists pre-defined unique values for the fields from the static header for each of the RDRs defined.

RDR Name	Sensor	TypeID	numAPIDS
OMPS LP Science	OMPS-LP	SCIENCE	2
OMPS LP Calibration	OMPS-LP	CALIBRATION	1
OMPS LP Diagnostic Exposure #1 Earth View	OMPS-LP	DIAGEXPONE	1
OMPS LP Diagnostic Exposure #2 Earth View	OMPS-LP	DIAGEXPTWO	1
OMPS LP Diagnostic Calibration	OMPS-LP	DIA-CAL	1

Appendix C. DQTT Quality Flag Mapping

Not Applicable

Appendix D. Abbreviations and Acronyms

See 470-00041 JPSS Program Lexicon for abbreviations and acronyms.

Attachment A. XML Formats for Related Data products

Table: ATT-1 XML Formats for Related Products

File Number	XML Filename
NA	NA